

Checking for AVX Compatibility with Pathfinder 2.x

The following steps will determine if your PC's processor is AVX-enabled and capable of running Pathfinder 2.x.

1. Download Coreinfo.zip from Microsoft at <https://docs.microsoft.com/en-us/sysinternals/downloads/coreinfo>
2. Extract Coreinfo.zip into a folder and open the folder.
3. Click the Windows Start button and type "cmd" (run the command prompt).
4. Drag and drop Coreinfo.exe into the command prompt.
5. Click somewhere in the black space of the command prompt.
6. Press the Enter key.
7. Accept the software license agreement.
After a few moments, several lines of text should be generated.
8. Use Ctrl+F to search for "AVX".
9. If the "*" character is next to AVX, your PC is AVX enabled and supports running Pathfinder 2.x.
If the "-" character is next to AVX, your PC is not AVX enabled and does not support running Pathfinder 2.x.

